

- (1) 初めに
- (2) SIP プロトコルでのアカウント設定例

---

(1) 初めに

Asterisk への、アジール SIP トランク アカウントの設定方法例を記載します。

サーバアドレスは、” [voip30\\*\\*.agile.ne.jp](#)”として設定例を記述しています。  
「[voip30\\*\\*](#)」部分はお客様それぞれ異なります。登録時にお伝えしたサーバアドレスをご記入ください。

**※本設定方法による機器の不具合等は保障致しかねます。お客様の責任にて設定をお願い致します。**

(2) SIP プロトコルでのアカウント設定例

SIP 内線3台([200~202](#))と SIP トランクの例  
(UID: [0000674356](#) , パスワード: [password](#) の場合)

```
-----  
sip.conf  
-----  
[general]  
allowguest=no  
maxexpire=3600  
defaultexpire=3600  
context=extd  
port=5060  
bindaddr=0.0.0.0  
srvlookup=yes  
disallow=all  
allow=ulaw  
language=jp  
  
register => 0000674356:password@siptr  
  
[siptr]  
type=friend  
username=0000674356  
secret=password  
context=inbound  
canreinvite=no  
host=voip30\*\*.agile.ne.jp  
insecure=port,invite  
disallow=all  
allow=ulaw
```

```
[200]
type=friend
username=200
secret=200pass
host=dynamic
```

```
[201]
type=friend
username=201
secret=201pass
host=dynamic
```

```
[202]
type=friend
username=202
secret=202pass
host=dynamic
```

```
-----
extensions.conf
-----
```

```
[general]
writeprotect=no
priorityjumping=yes
```

```
[inbound]
exten => s, 1,Dial(SIP/200&SIP/201&SIP/202,120,t)
exten => s, 2,Congestion
exten => s,102,Busy
```

```
[extd]
exten => _0., 1,Set(CALLERID(num)=0000674356)
exten => _0., 2,Dial(SIP/${EXTEN}@siptr,120,T)
exten => _0., 3,Congestion
exten => _0.,103,Busy
```

```
exten => _1., 1,Set(CALLERID(num)=0000674356)
exten => _1., 2,Dial(SIP/${EXTEN}@siptr,120,T)
exten => _1., 3,Congestion
exten => _1.,104,Busy
```

```
exten => _2XX, 1,Dial(SIP/${EXTEN},120,tT)
exten => _2XX, 2,Congestion
exten => _2XX,102,Busy
```